

1. Enhancements and Add Features

1) Check for Data File


Added the function to view changed/added drive-specific data files.

If the data files are the same as the server, you can overwrite them.

If changed, it will be changed/added.

You can check the changed data file selection at the restart of DriveView 9.


* The function works while the Internet is available.



2) Check the latest version

The ability to check for the latest version has been added.

If you are not using the latest version, provide a download link through an Internet browser.



* The function works while the Internet is available.

3) L100 model has been added.

2. Fix errors

1) Correction of S100 User Sequence Display Error

User sequence related parameters are not displayed on the user sequence screen when the drive has imported them. So when you read a parameter from the drive, changed the write value to display it on the user sequence screen.

2) Correct write error of parameter negative value

When writing parameters to the drive, the negative values correct the miswritten phenomenon. (Communication Data Value Conversion Error)

3) Correcting parameter initial write error

Other associated parameters have corrected the fact that parameter initials continue to be written.

4) Error displaying version mismatch message when connecting drive

The incorrect message has been corrected if the drive you are connecting to has a different code version of the project . We have made it more clearly expressed in addition.

5) Drive control button continuous click error

If you quickly and continuously clicked the drive control buttons (forward, reverse, stop, and reset), the graph stops on the trend screen has been corrected.

6) Fix other errors